brainaek

LEARN, PLAY, CODE, REPEAT.

FAQ on Robomaster EP Controls

A guide to achieve or address specific scenarios

slido.com #72453

Overview

- 1. Control Travel Speed
- **2.** LED Control
- **3.** Arm Control

Control Travel Speed

To control travel speed of Robomaster EP by:

- vxy <speed> and vz <speed> to move command
 vxy = speed in m/s at which the EP moves left-right-forward-backward (not more than 0.3m/s)
 vz = speed in degree/s at which the EP rotates (not more than 10)
- E.g. In DSTA's API:

Move to certain distance	robot.move('x 1 vxy 0.3')
Rotate 90 degree clockwise	robot.move('z 90 vz 10')
Gradually rotate 90 while moving forward (curve)	 robot.move('x 0.3 z 90 vxy 0.3 vz 10')
Move forward	robot.forward(0.3)

Rotate with robot.rotate cannot set speed. Must not use robot.rotate if you want to control rotation speed.

LED Control

To control LED color and effect using this SDK string:

led control comp <comp_str> r <r_value> g <g_value> b <value>
effect <effect_str>, where the effect remains after the instruction:

 <comp_str> refers to the LED on robotmaster</comp_str> 	 all → all LED, top_all → all LED on the gimbal Bottom_all → all LED on the chassis
color of LED	<r_value>,<g_value>,<b_value> : 0 – 255</b_value></g_value></r_value>
<effect></effect>	 one of these → solid, pulse, blink, scrolling
robomaster to show judge object detected	 robotsendcommand('led control comp bottom_all r 255 g 0 b 0 effect scrolling')
 Switch back to white after showing judge or during start of challenge 	 robotsendcommand('led control comp bottom_all r 255 g 255 b 255 effect solid')

Arm Control

To move the robot arm relative to its current position:
 robot.movearm() function to x_dist or y_dist

Note: The arm's current position is 0,0.


 To move robot arm with respect to the arm power-on position (RoboMaster SDK):

'robotic_arm moveto x <x_dist> y <y_dist>'

Note: Your robomaster are calibrated to the lowest point of X and Y but that is not '0,0'.

To find out the arm position (RoboMaster SDK):
 SDK 'robotic_arm position ?'

Note: That returns x, y. Do note the return value is of accuracy of ± -5 to ± -10 .



CAUTION:
DO NOT physically move the arm
by force when the robot is
executing an arm instruction or
powered on. This action will
damage the servo and is not
covered under warranty.